


1. News in Driver260:
 - MDR Data and Ctrl connection is supported on USB2 connection
2. The update process requires administrator rights.
3. The Windows Seven needs always additional RUN AS administrator rights. The first time installation runs only with Administrator Command Prompt, because the prompt to accept “always” the ZODIAC Data System GmbH as trusted provider needs interactive answer. When one time the provider is accepted then any follower installations or updates can be done to call direct the proper batch file.
4. Copy the folder Driver260 into a fixed disk of the computer to be updated.
5. The device can be present during the update process, but not necessary.
6. Let run the dplus32.bat if the Windows version is 32bit
7. Let run the dplus64.bat if the Windows version is 64bit.
8. The Windows 2K and XP operating system prompts for driver installation.
 - The Microsoft has no more recent driver than the installed one.



- Select always automatic installation procedure.



9. The update processes creates log file, dplus32.log or dplus64.log according to the selected update type.

10. News in Driver261:

- Windows 8 and Windows 8.1 are supported
- Windows 2012 server is supported
- Batch file dprem32.bat is added to remove drivers, only.
- Batch file dprem64.bat is added to remove drivers, only.

11. The dpremNN.bat files can be used to test failed driver removals when the operating systems had got corrupted. The created log file gives details to repair the windows to get success with the installation.